

Access your files


The cluster has a parallel file system which provides fast and reliable access to your data. You should have at least 3 file sets:

1. User home directory
 - For storing your persistent data
 - Located at /pfss/home/\$USER
 - Environment variable: **\$HOME**
 - The default quota is 10GB
2. User scratch directory
 - To be used for I/O during your job
 - Located at /pfss/scratch01/\$USER
 - Environment variable: **\$SCRATCH**
 - The default quota is 100GB
 - Inactive files may be purged every 30 days
3. Group scratch directory
 - For storing your files with your group mate
 - Located at /pfss/scratch02/\$GROUP
 - Environment variable: **\$SCRATCH_<GROUP NAME>**
 - The default quota is 1TB

There are three different ways to download or upload your files.

Web portal

We built a file browser in the portal. You may open it up by clicking files in the top menu bar.



The screenshot shows a web-based file manager interface. At the top, it says 'File Manager' with a close button (X). Below that, it shows storage usage: 'Used 2.631 / 10 GB (26.31%)'. There are links for 'new folder' and 'upload'. The breadcrumb path is '/ pfss / home / loki'. A toggle for 'hidden files: off' is on the right. The main area is a table with columns: Name, Size (with an upward arrow), and Last Modified. The table lists various files and folders, including 'R', 'Desktop', 'cuda-samples', and several .out and .ipynb files. Each row has a three-dot menu icon on the right.

Name	Size ▲	Last Modified	
R		2022.11.09 14:05	⋮
Desktop		2022.11.08 21:59	⋮
cuda-samples		2022.11.09 18:30	⋮
container.out	42 B	2022.11.12 21:58	⋮
cudaMPI.out	63 B	2022.11.10 12:18	⋮
tmux	161 B	2022.11.09 18:22	⋮
cudaMPI.sbatch	313 B	2022.11.10 12:16	⋮
hc.temp.sbatch	940 B	2022.11.12 21:58	⋮
jupyter.out	18 KB	2022.11.12 12:17	⋮
vnc.out	23 KB	2022.11.12 17:00	⋮
simpleMPI	28 KB	2022.11.10 12:09	⋮
testplot.ipynb	111 KB	2022.11.12 12:17	⋮
cudaOpenMP	790 KB	2022.11.09 18:41	⋮

You may switch between different file sets by clicking the hard disk icon. On top of that is the quota and consumption of the current file set. In the top right corner, there is a button for you to upload files. You may upload multiple files at once under a limit of 10GB. If you are uploading 1000+ files, we recommend you zip it before uploading, then unzip it in the web terminal.

Click on the item name to enter a directory or download a file. If it is a .sbatch file, the job launcher will be fired for enqueueing a new job. If it is a plain text file or any format that your browser can handle, it will be opened in a new tab. This comes in handy when viewing your job result without downloading it. There is a dropdown menu on the right-hand side to copy the path, rename, or delete an item.

SFTP

Another way is to use your favorite SFTP client. Download your access key from the home page. Below is an example using the Linux SFTP client.

```
# a strict file permission is required
chmod 400 loki-pri.pem

# remember to change loki to your own ID
sftp -i loki-pri.pem loki@ssh.hpccenter.hk
```

Mount to your local computer

When troubleshooting or profiling your application, you may check output files more often. So we provided a shortcut to mount the file set to your local computer using our CLI client.

It depends on SSHFS and is supported only in Linux and Mac OSX. Please make sure the command line **sshfs** is accessible.

First, you need to download and set up the CLI client on your computer. You should find everything on the web portal home page. Please make sure "Never send private key" is set to no to allow establishing an SSH connection through the client.

Command-line client

API Key: f35114cbb7fe9325104f46d84d9cc947

API Key Secret: [show secret](#)

Never send private key: No

Generate new API key

How to connect through the client:

1. Download the hc command-line client.

For Linux md5: b540a777b5d5598ac54a9558c981621a

For macOS md5: b75a0b2020282e69b6e739046a6073e2

For Windows md5: 21ec7cec59f0d9a7464bc672b2116725

2. Make executable with `chmod +x hc`

3. Run `./hc configure`

4. Input endpoint as `hpccenter.hk`

5. Input the above API key and API key secret.

6. Learn more with `./hc help`

Then you may list and mount file sets as follows:

```
$ hc filesystem-ls
```

ID	Type	Usage (GB)	Limit (GB)	Usage
home	USR	2.631	10	27%
scratch	USR	0	100	0%
scratch_appcara	GRP	0	1000	0%

```
$ hc filesystem-mount -t home -m ~/hpc-home
```

Mounted successfully.

Please use 'fusermount -u /home/loki/hpc-home' to unmount.

```
$ fusermount -u /home/loki/hpc-home
```

Revision #16

Created 4 November 2022 07:43:47 by Loki Ng

Updated 3 January 2023 05:38:35 by Loki Ng